



WINDOWS LIVE MAIL CONFIGURATION




1. Once you have opened Windows Live Mail (WLM) on your PC, click on the blue **File (1)** button in the top left corner, then click **Options (2)** and **Email Accounts (3)**.




2. In the Accounts window, click **Add**.



3. Choose **Email Account (1)**, then click **Next (2)**.



4. Enter your **Email Address(1)** & **Password (2)** as supplied by Hosting Australia. Then enter a **display name(3)**, which is what will show up in peoples inbox when you send an email. This can be anything you like. (Careful to use correct punctuation/spelling, as other people will see this!) Tick the box for **Manually Configure Servers (4)**. Click **Next**.



- 5.1. On the Configure Server Settings screen, complete as per below. Ensure you configure your **Incoming (1) & Outgoing server (2)** as below, See 5.2 for details. Also you make sure your **Logon User Name (2)** is set to the FULL email address & not the abbreviated default that WLM auto enters. Also change the **Outgoing Port to 26 (4)** & tick the **Requires Authentication (5)** Box. Click **Next**

Windows Live Mail

Configure server settings

If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information

Server type: POP

Server address: 1 mail.mydomain.com

Port: 110

Requires a secure connection (SSL)

Authenticate using: Clear text

Logon user name: 2 myaddress@mydomain.com

Outgoing server information

Server address: 3 mail.mydomain.com

Port: 4 26

Requires a secure connection (SSL)

5 Requires authentication

Cancel Back Next

5.2. If you aren't sure of your settings in step 5.1, they will be as follows. NOTE please replace your email address and domain name as required.

5.2.1. **EMAIL ADDRESS** – your full email address, i.e. myaddress@mydomain.com

5.2.2. **ACCOUNT TYPE** – generally this will be pop3, however, Hosting Australia servers do support IMAP.

5.2.3. **INCOMING & OUTGOING SERVER** – this will be [mail.\[MYDOMAIN\]](mailto:mail.[MYDOMAIN]), where [mydomain] will equal the name of your email domain, aka whatever follows the @ symbol in your email address. For example, if your email address is myaddress@mydomain.com, your incoming and outgoing server will be the highlighted section, i.e. mail.mydomain.com

5.2.4. **USERNAME** – This will be your **full** email address, i.e. myaddress@mydomain.com

5.2.5. **PASSWORD** – This will be your password, as configured when creating your email address, or as supplied by Hosting Australian tech support.

6. Click **NEXT**, and then click **FINISH**. Your WLM email client is now configured.

NOTE - If you require assistance with this, Hosting Australia can use Remote Desktop access to set your account up, but charges may apply. Please call 1300 761 930 for assistance.